

# **6** Safe Object Construction



John Barnes

This chapter covers a number of aspects of the control of objects. By objects here we mean both small objects in the sense of simple constants and variables of an elementary type such as Integer and big objects in the sense of Object-Oriented Programming.

Ada provides good control and flexibility in this area. This control is in many cases optional but the good programmer will use the features wherever possible and the good manager will insist upon them being used wherever possible.

## Variables and constants

As we have seen we can declare a variable or a constant by writing

| Top: Integer;                 | a variable |
|-------------------------------|------------|
| Max: constant Integer := 100; | a constant |

respectively. Top is a variable and we can assign new values to it whereas Max is a constant and its value cannot be changed. Note that when we declare a constant we have to give it a value since we cannot assign to it afterwards. A variable can optionally be given an initial value as well.

The advantage of using a constant is that it cannot be changed accidentally. It is not only a useful safeguard but it helps any person later reading the program and informs them of its status. An important point is that the value of a constant does not have to be static – that is computed at compile time. An example was in the program for interest rates where we declared a constant called Factor

```
function Nfv_2000 (X: Float) return Float is
Factor: constant Float := 1.0 + X/100.0;
begin
return 1000.0 * Factor**2 + 500.0 * Factor – 2000.0;
end Nfv_2000;
```

Each call of the function Nfv\_2000 has a different value for X and so a different value for Factor. But Factor is constant throughout each individual call. Although this is a trivial example and it is clear that Factor is not changed during execution of an individual call nevertheless we should get into the habit of writing **constant** whenever possible.

Parameters of subprograms are another example of variables and constants.

Parameters may have three modes: in, in out, and out. If no mode is shown then it is in by default. All parameters of functions must be of mode in.

A parameter of mode in is a constant whose value is given by the actual parameter. Thus the parameter X of Nfv\_2000 has mode in and so is a constant –

this means that we cannot assign to it and so are assured that its value will not change. The actual parameter can be any expression of the type concerned.

Parameters of modes **in out** and **out** are variables. The actual parameter must also be a variable. The difference concerns their initial value. A parameter of mode **in out** is a variable whose initial value is given by that of the actual parameter whereas a parameter of mode **out** has no initial value (unless the type has a default value such as **null** in the case of an access type).

Examples of all three modes occur in the procedures Push and Pop in the chapter on Safe Architecture

procedure Push(S: in out Stack; X: in Float);
procedure Pop(S: in out Stack; X: out Float);

The rules regarding actual parameters ensure that constancy is never violated. Thus we could not pass a constant such as Factor to Pop since the relevant parameter of Pop has mode **out** and this would enable Pop to change Factor.

The distinction between variables and constants also applies to access types and objects. Thus if we have

type Int\_Ptr is access all Integer; K: aliased Integer; KP: Int\_Ptr := K'Access; CKP: constant Int\_Ptr := K'Access;

then the value of KP can be changed but the value of CKP cannot. This means that CKP will always refer to K. However, although we cannot make CKP refer to any other object we can use CKP to change the value in K by

CKP.all := 47; --- change value of K to 47

On the other hand we might have

type Const\_Int\_Ptr is access constant Integer; J: aliased Integer; JP: Const\_Int\_Ptr := J'Access; CJP: constant Const\_Int\_Ptr := J'Access;

where the access type itself has **constant**. This means that we cannot change the value of the object J referred to indirectly whether we use JP or CJP. Note that JP can refer to different objects from time to time but CJP cannot. Of course, the value of the object J can always be changed by a direct assignment to J.

Safe object construction

# Constant and variable views

Sometimes it is convenient to enable a client to read a variable but not to write to it. In other words to give the client a constant view of a variable. This can be done with a so-called deferred constant and the access types just described.

A deferred constant is one declared in the visible part of a package and for which we do not give an initial value. The initial value must then be given in the private part. Consider the following

```
package P is
type Const_Int_Ptr is access constant Integer;
The_Ptr: constant Const_Int_Ptr; -- deferred constant
private
The_Variable: aliased Integer;
The_Ptr: constant Const_Int_Ptr := The_Variable'Access;
```

end P;

The client can read the value of The\_Variable indirectly through the object The\_Ptr of type Const\_Int\_Ptr by writing

K := The\_Ptr.**all**; -- indirect read of The\_Variable

But since the access type Const\_Int\_Ptr is declared as **access constant** the value of the object referred to by The\_Ptr cannot be changed by writing

The\_Ptr.**all** := K; --- illegal, cannot change The\_Variable indirectly

However, any subprogram declared in the package P can access The\_Variable directly and so write to it. This technique is particularly useful with tables where the table is computed dynamically but we do not want the client to be able to change it.

The named access type is not really necessary since we can equally write

package P is The\_Ptr: constant access constant Integer; -- deferred constant private The\_Variable: aliased Integer; The\_Ptr: constant access constant Integer := The\_Variable'Access; ...

end P;

Note the double use of **constant** in the declaration of The\_Ptr. The first says that The\_Ptr is itself a constant. The second says that it cannot be used to change the value of the object that it refers to.

# Limited types

The types we have met so far (Integer, Float, Date, Circle and so on) have various operations. Some are predefined, such as the equality operation to compare two values (with =) and some also have user-defined operations, such as Area in the case of the type Circle. The operation of assignment is also available for all the types mentioned so far.

Sometimes assignment is undesirable. There are two main reasons why this might be the case

- the type might represent some resource such as an access right and copying could imply a violation of security,
- the type might be implemented as a linked data structure and copying would simply copy the head of the structure and not all of it.

We can prevent assignment by declaring the type as **limited**. A good illustration of the second problem occurs if we implement the stack using a linked list. We might have

package Linked\_Stacks is
 type Stack is limited private;
 procedure Clear(S: out Stack);
 procedure Push(S: in out Stack; X: in Float);
 procedure Pop(S: in out Stack; X: out Float);

## private

type Cell is record Next: access Cell; Value: Float; end record;

type Stack is access all Cell; end Stacks;

The body might be

package body Stacks is

procedure Clear(S: out Stack) is
begin
 S := null;
end Clear;
procedure Push(S: in out Stack; X: in Float) is
begin
 S := new Cell'(S, X);
end Push;

Safe object construction

```
procedure Pop(S: in out Stack; X: out Float) is
begin
    X := S.Value;
    S := Stack(S.Next);
end Pop;
```

end Stacks;

This uses the normal linked list style of implementation. Note that the type Stack is declared as limited private so that assignment of a stack as in

This\_One, That\_One: Stack; ... This\_One := That\_One; -- illegal, type Stack is limited

is prohibited. If assignment had been permitted then all that would have happened is that This\_One would end up pointing to the start of the list defining the value of That\_One. Calling Pop on This\_One would simply move it down the chain representing That\_One. This sort of problem is known as aliasing – we would have two ways of referring to the same entity and that is often very unwise.

In this example there is no problem with declaring a stack, it is automatically initialized to be null which represents an empty stack. However, sometimes we need to create an object with a specific initial value (necessary if it is a constant). We cannot do this by assigning in a general way as in

type ⊺ is limited ...

X: constant T := Y; -- illegal, cannot copy value in variable Y

because this involves copying which is forbidden since the type is limited.

Two techniques are possible. One involves aggregates and the other uses functions. We will consider aggregates first. Suppose the type represents some sort of key with components giving the date of issue and the internal code number such as

```
type Key is limited
record
Issued: Date;
Code: Integer;
end record;
```

The type is limited so that keys cannot be copied. (They are a bit visible but we will come to that in a moment.) But we can write

K: Key := (Today, 27);

since, in the case of a limited type, this does not copy the value defined by the aggregate as a whole but rather the individual components are given the values Today and 27. In other words the value for K is built *in situ*.

It would be more realistic to make the type private and then of course we could not use an aggregate because the components would not be individually visible. Instead we can use a constructor function. Consider

```
package Key Stuff is
 type Key is limited private;
 function Make_Key( ... ) return Key;
 ...
private
 type Key is limited
   record
     Issued: Date:
     Code: Integer;
   end record;
end Key_Stuff;
package body Key_Stuff is
 function Make Key( ... ) return Key is
 beain
   return New Key: Key do
     New Key.Issued := Today;
     New Key.Code := ... ;
   end return:
```

end Make\_Key;

end Key\_Stuff;

The external client (for whom the type is private) can now write

My\_Key: Key := Make\_Key( ... ); -- no copying involved

where we assume that the parameters of Make\_Key are used to compute the internal secret code.

It is worth carefully examining the function Make\_Key. It has an extended return statement which starts by declaring the return object New\_Key. When the result type is limited (as here) the return object is actually built in the final destination of the result of the call (such as the object My\_Key). This is similar to the way in which the components of the aggregate were actually built *in situ* in the earlier example. So again no copying is involved.

The net outcome is that Ada provides a way of creating initial values for objects declared by clients and yet prevents the client from making copies. The

limited type mechanism gives the provider of resources such as the keys considerable control over their use.

# **Controlled types**

Ada provides a further mechanism for the safe management of objects through the use of controlled types. This enables us to write special code to be executed when

- 1) an object is created and,
- 2) when it ceases to exist and,
- 3) when it is copied if it is of a nonlimited type.

The mechanism is based on types called Controlled and Limited\_Controlled declared in a predefined package thus

package Ada.Finalization is
type Controlled is abstract tagged private;
procedure Initialize(Object: in out Controlled) is null;
procedure Adjust(Object: in out Controlled) is null;
procedure Finalize(Object: in out Controlled) is null;

type Limited\_Controlled is abstract tagged limited private; procedure Initialize(Object: in out Limited\_Controlled) is null; procedure Finalize(Object: in out Limited\_Controlled) is null; private

## end Ada.Finalization;

The central idea (for a nonlimited type) is that the user declares a type which is derived from Controlled and then provides overriding declarations of the three procedures Initialize, Adjust and Finalize. These procedures are called when an object is created, when it is copied, and when it ceases to exist, respectively. Note carefully that these calls are inserted automatically by the system and the programmer does not have to write explicit calls. The same mechanism applies to a limited type which has to be derived from Limited\_Controlled but there is no procedure Adjust since copying is not permitted. These operations are typically used to provide complex initializations, deep copying of linked structures, storage reclamation at the end of the lifetime of an object, and other housekeeping activities that are specific to the type.

As an example, suppose we reconsider the stack and decide that we want to use the linked mechanism (so there is effectively no upper bound to the capacity of the stack) but wish to allow copying one stack to another. We can write

```
package Linked_Stacks is
  type Stack is private;
  procedure Clear(S: out Stack);
  procedure Push(S: in out Stack; X: in Float);
  procedure Pop(S: in out Stack; X: out Float);
private
  type Cell is
```

record Next: access Cell; Value: Float; end record:

type Stack is new Controlled with record Header: access Cell; end record;

overriding
procedure Adjust(S: in out Stack);
end Linked\_Stacks;

The type Stack is now just private. The full type shows that it is actually a tagged type derived from the type Controlled and has a component Header which effectively is the stack in the previous formulation. In other words we have introduced a wrapper. Note that the user cannot see that the type is controlled and tagged. Since we want to make assignment work properly we have to override the procedure Adjust. Note also that we have supplied the overriding indicator so that the compiler can double check that Adjust does indeed have the correct parameters.

The package body might be

package body Linked\_Stacks is

```
procedure Clear(S: out Stack) is
begin
    S := (Controlled with Header => null);
end Clear;
procedure Push(S: in out Stack; X: in Float) is
begin
    S.Header := new Cell'(S.Header, X);
end Push;
procedure Pop(S: in out Stack; X: out Float) is
begin
    X := S.Header.Value;
```

Safe object construction

S.Header := S.Header.Next; end Pop; function Clone(L: access Cell) return access Cell is begin if L = null then return null; else return new Cell'(Clone(L.Next), L.Value); end if; end Clone; procedure Adjust(S: in out Stack) is begin S.Header := Clone(S.Header); end Adjust; end Linked\_Stacks;

Assignment will now work properly. Suppose we write

This\_One, That\_One: Stack;

This\_One := That\_One; -- calls Adjust automatically

The raw assignment of That\_One to This\_One copies just the record containing the component Header. The procedure Adjust is then called automatically with This\_One as parameter. Adjust calls the recursive function Clone which actually makes the copy. This process is often called a deep copy. The result is that This\_One and That\_One now contain the same elements but are otherwise disjoint structures.

Another notable point is that the procedure Clear sets the parameter S to a record whose header component is null; the structure is known as an extension aggregate. The first part of the extension aggregate just gives the name of the parent type (or the value of an object of that type) and the part after **with** gives the values of the additional components, if any. The procedures Pop and Push are straightforward.

The reader might wonder about reclamation of unused storage when Pop removes an item and also when Clear sets a stack to empty. This will be discussed in the next chapter when we consider memory management in general.

Note that Initialize and Finalize are not overridden and thus inherit the null procedure of the type Controlled. So nothing special happens when a stack is declared – this is correct since we just get a record whose Header is null by default and nothing else is required. Also nothing happens when an object of

type Stack ceases to exist on exit from a procedure and so on - this again raises the issue of the reclamation of storage and will be addressed in the next chapter.

North American Headquarters 104 Fifth Avenue, 15th floor New York, NY 10011-6901, USA tel +1 212 620 7300 fax +1 212 807 0162 sales@adacore.com www.adacore.com European Headquarters 46 rue d'Amsterdam 75009 Paris, France tel +33 1 49 70 67 16 fax +33 1 49 70 05 52 sales@adacore.com www.adacore.com

